

## نصب ویندوز 10

### پیش نیازهای لازم برای نصب ویندوز

برای اینکه بتوانید از ویندوز ۱۰ استفاده کنید نیاز به یک حداقل سخت افزار و پیش نیازهایی خواهید داشت که شامل موارد زیر هستند.

حداقل پردازنده ۱ گیگاهرتز

رم ۱ گیگابایت (نسخه ۳۲ بیت) و ۲ گیگابایت (نسخه ۶۴ بیت)

فضای آزاد هارد دیسک ۱۶ گیگابایت (نسخه ۳۲ بیت) و ۲۰ گیگابایت (نسخه ۶۴ بیت)

Microsoft DirectX 9 graphics device with WDDM 1.0 driver کارت گرافیک

فایل حاوی ویندوز و نصب آن از طریق سی دی یا حافظه فلش

# مرحله اول: بوت سیستم

کیبورد DELETE یا DEL سیستم خود را ریستارت کنید و قبل از شنیدن صدای بیپ و بالا آمدن مشخصات بایوس کلید برای این کار استفاده کنید. F12 و در برخی از مادربردها F2 خود را چند بار فشار دهید. یا اینکه با استفاده از کلیدهای عمومی ترین حالت است و تقریباً در اکثر سیستم‌ها استفاده از همین کلید پاسخ خواهد داد. DEL کلید



# BIOS SETUP UTILITY

## Boot

### Boot Device Priority

1st Boot Device	[CDROM:PO-PIONEER D]
2nd Boot Device	[IDE:WDC WD1002FAEK]
3rd Boot Device	[Disabled]

Specifies the boot sequence from the available devices.

A device enclosed in parenthesis has been disabled in the corresponding type menu.

↔ Select Screen  
↑↓ Select Item  
+- Change Option  
F1 General Help  
F10 Save and Exit  
ESC Exit

MIZBANFA MAG

v02.61 (C) Copyright 1985-2009, American Megatrends, Inc.

# BIOS SETUP UTILITY

## Main Ai Tweaker Advanced Power **Boot** Tools Exit

### Boot Settings

- ▶ **Boot Device Priority**
- ▶ Hard Disk Drives
- ▶ Boot Settings Configuration
- ▶ Security

Specifies the Boot Device Priority sequence.

A virtual floppy disk drive (Floppy Drive B: ) may appear when you set the CD-ROM drive as the first boot device.

↔ Select Screen  
↑↓ Select Item  
Enter Go to Sub Screen  
F1 General Help  
F10 Save and Exit  
ESC Exit

MIZBANFA MAG


v02.61 (C) Copyright 1985-2009, American Megatrends, Inc.

- به این نکته توجه داشته باشید که، برای بوت شدن از طریق فلش باید قبل از اینکه وارد محیط بایوس شوید، وارد کرده باشید تا سیستم آن را شناسایی کند. در غیر این صورت USB حافظه فلش دیسک خود را در درگاه باید از بایوس خارج شده و بعد از قرار دادن حافظه فلش در یو اس بی مراحل گفته شده را طی کنید

شروع نصب ویندوز

Press any key to boot from CD or DVD....\_





# Settings

## Express settings

We recommend these settings, which include occasionally sending info to Microsoft. You can customize these settings now or later.

- Automatically find and connect to devices and content on this network.
- Automatically install Windows updates, app updates, and device software.
- Turn on Do Not Track in Internet Explorer.
- Help protect your PC from unsafe files, apps, and websites, and check online for solutions to problems.
- Help improve Microsoft software, services, and location services by sending us info.
- Use Bing to get search suggestions and web results in Windows Search, and let Microsoft use your location and other info to personalize your experiences.
- In Internet Explorer, use page prediction to preload pages, which sends your browsing history to Microsoft.
- Let Windows and apps use your name, account picture, and advertising ID, and request your location from the Windows Location Platform.

[Learn more about express settings](#)

[Privacy statement](#)



Use express settings

Customize

## ← Sign in to your Microsoft account

Sign in to easily get your online email, photos, files, and settings (like browser history and favorites) on all your devices. You can manage your synced settings at any time.

Don't have an account?

[Create a new account](#)

[Privacy statement](#)



Next

## ← How should we set up your PC?

Copy your settings and Windows Store apps from another PC, or set this up as a new PC.

 Parallels Software International Inc. (LOWELLHEDDI437E)  
Last saved 10/1/2014

[Show all my PCs](#)

 **Set this up as a new PC instead**


Sync my Start screen layout



Next

## ← OneDrive is your cloud storage

Your camera roll and PC settings will automatically be backed up to the cloud, and new documents you create will be saved to OneDrive by default. That way, you can get to them from any device, even if something happens to your PC.



Turn off these OneDrive settings (not recommended)

[Privacy statement](#)

**MIZBANFA**MAG

Next

You can get new apps from the Store

Installing your apps